

Co-Hosting Settings – SAM Broadcaster

The following settings is one configuration you can use to setup your system to take calls and live interviews.

Requirements

- 1. Skype
- 2. Broadcasting Software (SAM Broadcaster, PlayIt Live, etc.)
- 3. Virtual Audio Cables
- 4. VoiceMeeter Banana

Skype Settings

Set the microphone to Line 2 and Speakers to Line 1

S Skype - Options		
S General	Audio settings: Set up sound on your computer	
General settings	Line 2 (Virtual Audio Cable)	
9 Audio settings	Volume High	
 Sounds 	Automatically adjust microphone settings	
Video settings	♦ Speakers Line 1 (Virtual Audio Cable)	
œ Skype WiFi	Volume Automatically adjust speaker settings	
Skype Translator	■ Ringing Use selected speaker ▼	
Privacy		
Notifications	Show	advanced options
📞 Calls		
IM & SMS	Other things you can do	
Advanced	Make a free test call	
	Learn more about setting up your audio equipment	
	Sar	re Cancel



SAM Settings

Set the Record Soundcard device to **Voicemeeter Output**, the Output device to **Voicemeeter Input** and **Cue Output** device to **Line 2**. This is what will enable people on the phone to hear music from SAM.

VoiceFX configuration VoiceFX destination (Recording mode) None (Auto fade only) Music fade out Soundcard (Skip audio pipeline) Encoders (Record to pipeline, skip output) VoiceFX destination (Record to pipeline) Nime Time Time Time Time Time Time Time T	s Deck B Sound FX Voice FX Aux 1 Mixer Output t Settings Buffer Settings triver Packets 10
Voice FX destination (Recording mode) C None (Auto fade only) C Mixer (Record to pipeline) C Soundeard (Skip audio pipeline) C Encoders (Record to pipeline, skip output) C Encoders (Record to pipeline) C Encoders (Reco	Deck B Sound FX Voice FX Aux 1 Mixer Output t Settings Buffer Settings triver Packets 10
Recording settings 00% Record driver 00% DirectSound recorder 00% Record driver 00% VoiceMeeter Output (VB-Audio Voirtig) 00% Buffer settings 1.0 sec Packets 5 9 00% Maximum latency: 50 ms 00ms	levice 20 eeter Input (VB-Audio VoiceMeeter ▼ at Settings le cue output channel channels rate sound device ut driver und output ▼ ce /ittual Audio Cable) ▼

Voice Meter Settings

The settings below will allow you to hear the music from SAM as well as from Skype. Set you mic on **Channel 1**, Skype Speakers (**Line 1**) on **Channel 2 and** your speakers/headphones to **A1/A3**. Make sure **A1/A3** is selected to listen on the appropriate device.

